

## Addendum 1

### Local Network License

Perfect PDF 6 product family offers two types of license:

- 1) Workstation (single user) license
- 2) Network license

The workstation license allows the installation and use of a Perfect PDF 6 product on a single operating system on a single computer. Installation on a second computer requires that the software be uninstalled on the first computer. Two or more simultaneous installations under one license are not allowed. This restriction also applies to Terminal Server clients – one license is required for each client using the software.

The local network license (LNL) is for use on a local network with multiple clients (including Terminal Server or Citrix clients). This license connects the software with a server on the network. As a result, it is not necessary to activate the software on each workstation separately. The license is valid only for the number of clients on the network. The software can be installed on each client automatically. A silent installation is also possible (see the [description](#) for more details).

The LNL system service is the "soft Xpansion Local Network License". It can be installed on a server (any Windows computer) by a system administrator and started automatically without rebooting. A special setup routine is employed during installation. Silent installation is also supported. The service uses port 32 by default but the system administrator may specify an alternate port. Please ensure that the selected port is not blocked by your firewall.

The service uses its own hardware-bound license.

You can view and alter the status and setting of the service via a web-based interface located at:

`http://server-name:port-number`

Via the web interface you can:

- View the license state
- Change properties:
  - o activate / deactivate LNL server
  - o Service autostart
  - o Port number
- View the list of registered users
- View the list of registered workstations

The service does not create a network or Internet connection.

Perfect PDF 6 software can be used on an arbitrary workplace as long as the service is installed on your server and (automatically) running, and as long as the appropriate port is open. The number of installations (clients) will be counted and compared with to the maximum number permitted by the license. Each client that runs the software will be counted as an installation and registered. Both computer names and user names will be counted and registered in two corresponding lists. Once either list exceeds the maximum number of clients permitted, the software will not start on additional clients.

The clients will identify the server using its IP address or its computer name. The clients can receive this information using one of three methods:

- 1) Before you begin installing the clients, you submit your server's IP address and port number to the soft Xpansion support team. Soft Xpansion will then provide you with a setup program using this data.
- 2) Copy the file "product.license" to a folder on the client. The file and the folder will be specified by soft Xpansion. This file will contain the following information:
  - customer name (name of your company)
  - server IP address
  - port number
- 3) The connection will be established after the client is installed. When a Perfect PDF 6 program starts up, it will check to see if there is a network connection. If no connection exists, a dialogue window will appear and you'll be able to configure the required network settings. Click "Change Settings" and enter the IP address and port number of the license server.

If you want to test LNL, a test license for up to ten clients is available. The test license will allow you to run the software in demo mode. There are no time or feature limits in this mode, but all PDFs will be watermarked.

## Addendum 2

### Silent Installation

Perfect PDF 6 software can also be installed in “silent mode” – without a user interface. In this case, the installation files should be distributed to the clients by the system administrator and started with administrator privileges.

Depending on the parameters you set, the installation will run in interactive or silent mode and the system will or will not reboot afterwards.

The command line and parameter list:

```
setup.exe <parameter> <parameter> ...
```

- 1) No parameter  
Product installation, interactive mode.
- 2) /i  
Product installation.
- 3) /x<Product ID>  
Uninstall the product with the specified ID, e.g.: "/x{A6D309F9-38AB-4cc3-8DA7-0544F5011788}".
- 4) /qn  
Silent installation. If the parameters “/norestart” or “/forcerestart” are not set, Windows will reboot only if necessary (if, for example, a new driver was installed).
- 5) /norestart  
Never reboot after installing.
- 6) /forcerestart  
Always reboot after installing.